

# Seiten anlegen und einstellen

## Konfiguration anzeigen

EINSTELLUNGEN

PLAKETTEN

SICHT

✓

Im visuellen Editor bearbeiten

In YAML bearbeiten

Titel

Symbol

URL

Aussehen

### Ansichtsart

☒ Rasteransicht (Standard)

☐ Seitenleiste

☐ Panel (1 Karte)

Unteransicht

☐

Unteransichten erscheinen nicht in Registerkarten und haben eine Zurück-Schaltfläche.

You have layout-card installed which adds some options to this dialog.  
Please see [layout-card on github](#) for usage instructions.

ABBRECHEN

SPEICHERN

bei der Seitenerstellung bitte die YAML anpassen

```
theme: Backend-selected
title: Büro
path: buro
type: custom:vertical-layout
subview: false
badges: []
```

Jetzt geht es an die Grundstruktur des ersten Raumes hier habe ich meist folgende Config:

```
type: vertical-stack
cards:
  - type: custom:mushroom-chips-card
    chips:
      - type: template
        icon: mdi:arrow-left-bold
        picture: ""
        content: Home
        tap_action:
          action: navigate
          navigation_path: /lovelace-yotube/smartphonehome
      - type: entity
        entity: sensor.TEMPERATUR
      - type: entity
        entity: sensor.LUFTFEUCHTIGKEIT
    - type: custom:mushroom-template-card
      primary: Lichter
      secondary: ""
      icon: ""
    - type: vertical-stack
      cards: []
    - type: custom:mushroom-template-card
      primary: Geräte
      secondary: ""
      icon: ""
    - type: vertical-stack
      cards: []
    - type: custom:mushroom-template-card
      primary: Heizung
      secondary: ""
      icon: ""
    - type: vertical-stack
```

```
cards: []  
- type: custom:mushroom-template-card  
  primary: Sonstiges  
  secondary: "  
  icon: "  
- type: vertical-stack  
  cards: []
```

---

Revision #1

Created 17 March 2023 11:11:40 by Cryd

Updated 17 March 2023 11:11:44 by Cryd